DOCUMENTATION OF ROSA-i

Author: Ananth (Version1)

Ram yashree B K (Version 1.1)

1. HOW TO SETUP RASPBERRY PI:

HERE ARE THE STEPS TO SETUP THE RASPBERRY PIUSING COMMAND PROMPT:

- sudo nano/etc/dphys-swapfile
- Commentor use # in the place of

 $C O N F _ S W A P S I Z E = 100$

C O N F _ S W A P S I Z E = 2 0 4 8

- 1. sudo apt-getinstall build-essential cm ake pkg-config
 - 2. sudo apt-getinstall libjpeg-dev libtiff5-dev libjasper-dev libpng 12-dev
 - 3. su do apt-get in stall libav co dec-dev libav form at-dev libsw scale-dev lib v 41-dev
 - 4. sudo apt-getin stall lib x vid core-dev lib x 2 6 4 de v
 - 5. sudo apt-get in stall lib g tk 2.0 dev lib g tk 3 dev
 - 6. sudo apt-getin stall libatlas-base-dev g fortran
- 1. sudo apt-getinstall python 3-dev
 - 2. sudo apt-getinstall python 3-pip
- 1. wget-Oopencv.zip https://github.com/opencv/opencv/archive/4.1.0.zip
 - 2. w get -O opencv_contrib.zip https://github.com/opencv/opencv_contrib/archive/4.1.0.zip
 - 3. unzip opencv.zip
 - 4. unzip opencv_contrib.zip
- sudo pip3 install num py
- 1. cd ~/opencv-4.1.0
 - 2. m kdir build
 - 3.cd build
 - 4. cm ake -D CM AKE_BUILD_TYPE=RELEASE \
 - -D C M A K E _ I N S T A L L _ P R E F I X = /u s r/lo c a l \
 - -D INSTALL_PYTHON_EXAMPLES = ON \

 - D B U I L D $_$ E X A M P L E S = O N ...
- make-j4(This step will take time...)
- sudo make install & & sudo ldconfig
- sudo reboot

= = >

$2 \;.\;\; \mathsf{IN}\;\mathsf{S}\;\mathsf{T}\;\mathsf{A}\;\mathsf{L}\;\mathsf{L}\;\mathsf{A}\;\mathsf{T}\;\mathsf{IO}\;\mathsf{N}\;\;\mathsf{O}\;\mathsf{F}\;\;\mathsf{R}\;\mathsf{O}\;\mathsf{S}\;\mathsf{A}\;\;\mathsf{I}$

• OPEN BROWSER ON RASPBERRY PI

• LOGIN TO GITHUB (USERNAME: hydaxiso@gmail.com, PASSWORD: Hydax@iso2018) • Go to hydax hydraulics ROSA I folder Copy url Open term in al and type code git clone ctrl+v New folder will be created named ROSA-i Open Rosa-I folder • Create new folder (Name: train_img) • Inside this folder create 4 new folders (folder A, folder B, folder C & folder D) 3. Creation of sub-folders in Rosa-i: create 4 folders, it should be case sensitive with name: folderA, folderB, folderC, folderD. (This is Optional) • installation process of raspberry pi O S in a new sd card: • 1.https://www.raspberrypi.org/documentation/installation/installing-images/ download this im age r u n select os: raspberry with recom mended software select storage: m em ory card through card reader or pen drive w rite The OS will be installed and ready for the boot up and start • --> ANY ISSUES WITH THE RASPBERRY PI, FOLLOW THIS INSTRUCTIONS: https://learn.pim oroni.com/tutorial/pi-lcd/getting-started-withraspberry-pi-7-touchscreen-lcd • --> if PIL, im ageTk, Im age gives error, • go to the term in al check python version it should be above 3.0 version if yes, follow the two commands -- - * - - - - - python3 -m pip install -- upgrade pip python3 -m pip install -- upgrade Pillow

4. BOOTPROCESS: Things to do to run the program on bootup: Modify the . bashrc file To do that, open term inaltype: sudo nano /hom e/pi/.bashrc Then a screen appears, which is bashrc file We need to edit that file; we can follow the following steps. Just type, echo running at boot sudo python 3.7 /hom e/pi/rosa---i/updation_for_rosa-i.py These were the commands, that to be used. here /home/pi is default.rosa---i/updation_for_rosa-i.py is myfolder. U can direct it to urpython path, by just clicking the path shown in destination file. Just after running two command lines, press CTRL+x □ Y□ enter. su do reboot Before all, check the python version, if not upgraded. kindly upgrade to latest version or at least python 3 and above. install pip install pip sudo apt-getinstall python 3-pil.im agetk (if you are using python 3 and above). Hopefully, this will clear all the import errors. Important steps to follow when dealing with os: · On the top of the program, let's say line one type:-• #! /usr/bin/env

os.chdir("home/pi/rosa-i/") [inside brackets, we need to provide path of the

• python importos

file.]

5. THE ROSA-ICODE EXPLAINATION:

This is a program which uses python with tkinter framework for GUI.

- 1. Imported all dependencies required for ROSA-i.
- $2. \quad First \ three \ lines \ is \ for \ bootup \ process, it \ is \ directly \ linked \ to \ Linux \\ storage$
- 3. Setting up the tkinter UI window to the required size.
- 4. Initialized all the photoIM AGE, for UI
- 5. Then we defined function, according to the four main parts: TEACH, OPEN, TOOLS and HELP
- 6. Let's move to the TEACH option.
 - Here we are declaring global variable for some photos, which is done because sometimes the photos goes to garbage collector.
 - Then, made a window which can fit to the screen with labels as
 - Coming to the:: path A:: and remaining paths, we have initialized the path as iteration path because in future we will be using glob.glob
 - window. Destroy is used to destroy the window
 - Then each button has specific function which is to be executed according to the need. below will be discussing about the button functionalities.
 - W hen teach is pressed, the user can have only four snaps as per this rosa-i (ver 1.0) software.
 - There are 4 folders, where we can save the snaps in the required folders. Choosing it takes to the particular folder creates file as 1,2,3,4. A fter this, it starts estimating the nonblack pixels going into the folder
 - D e f e s t 1 ():
 - here, i created two empty list, applying for loop over path folder using glob.glob

```
The reason i= 2, because we have comparing first image and other
  three im ages in that folder in for loop.
 By using subtract (photo1, photo2), we are able to extract the
  non-colliding pixels out.
if photo1.shape==photo all.shape:
      diff = cv2.subtract(photo1,photo all)
      non black pix = np.sum(diff!=0)
  Diff! = 0, extracts all the non-white pixels and assigned
 to non_black_pix.
  We need to have 4 comparisons, 1-2,1-3,1-4,2-3
  Use the same way of reading for comparison and append the
  values in the empty list \square NonBP = []
 Then we need to find standard deviation, use the form ulas with
 help of code.
        Mean = sum(NonBP)/len(NonBP)
        Var = sum(pow(i_v - Mean,2) for i_v in NonBP)/len(NonBP)
        Std dev = math.sqrt(Var)
        print("Mean is ",Mean)
        #calc.append(Mean)
        print("Std dev",Std dev)
        #calc.append(Std dev)
        Uthreshold = Mean+Std dev
        Lthreshold = Mean-Std dev
   Append the uthreshold to the calc[], so that we can parse and put
   it in the csv file.
   form at. Path = (initialize a new if do not exist)
   with open (Path, "w", new line = "") as file:
        (any nam e) writer = csv.writer
         writer.writerow(row_list)
  To create csv file, follow the Follow the same pattern
  to create sim ilar functionalities with help of function.
  Checking the file if it contains any file then disable. The procedure
  is this. line from 641 to 673.
```

```
Open CV camera initialization. And then changing its frame to
             black and white form at and linking the path to the file.
             End of teach option.
7. OPEN window:
                Here, we have test window and a folder option.
                We have to select the folder and then press test button to test the
                testing object with the master object.
                Here, we have created the choose the folder function, where we
                have created the empty list
                We are comparing the first image of any of the folders present in
                the directory (which is defined as path or set according to the
                path) to the test im age.
                Test image is captured
                                               when the
                The value of uthreshold is stored in csv file .so to read that csv
                file and used in as if nonblack pixels
                > uthreshold or not, then resulting in Accepted and Rejected
                accordingly.
                So, reading the csv file happens from these lines, were before these
                lines initialization and path is set to respective folders.
                 #1 need to load csv file nere
                 filee = path for csvfile
                 print(filee, "this path is for csv file")
                 with open(filee, "r") as letscsv:
                      csv reader = csv.reader(letscsv)
                      for line in csv reader:
                           print(line,":")
                           print(len(line))
                           compute value=line.pop(0)
                           print("compute value",compute value)
                           Uthreshold = int(float(compute value))
                           print(type(Uthreshold))
                           break
```

Comparing of im ages is done as we did in teach screen,

```
if imggrayed.shape == template.shape:
    difference = cv2.subtract(imggrayed,template)

x= np.sum(difference!=0)
    #print(difference.shape)
    print("non_black_pixels",x)
    non_black_pixels = x.item(0)
    print(type(non_black_pixels))
```

According to the nonblack pixels value from teach window -any folders file -firstim age (which is done by reading the path of that path and assigning to any random variable to the testim age path (difference value of them)

```
ff = (fla+"/Result.csv")
 #ff=("/home/pi/ROSA---i/train images/folderA/Results.csv")
 with open(ff, "a", newline="") as file:
     if non black pixels > Uthreshold:
         print("non black pixel is greater than uthreshold")
         circlee= PhotoImage(file="reject1.png")
         circleebtn=Button(window2,image = circlee,border=0,bg="white")
         circleebtn.image = circlee
         circleebtn.place(relx=0.4, rely=0.5, relwidth=0.27, relheight=0.12)
         count()
         today = datetime.now()
         d1 = today.strftime("%d/%m/%Y %H:\M:\S")
         row list = ['Rejected',d1]
         writer = csv.writer(file)
#currentdatetime = datetime.now()
         writer.writerow(row list)
         window2.update()
         window2.after(2000,delete img1())
```

- Create a Reslut.csv to store result of test im age.
- if non_black_pixels > U threshold:
 then its rejected so i have given the im age which is rejected
 im age on the live video (which is done by OpenCV). Call

count() function (refer below im age) to count the rejected

```
im ages and store the result with current date and time in csv
file.
def count():
     global buttonclick
     global 13
     buttonclick += 1
     13.configure(text= " 0" + str(buttonclick))
 else:
     print("this statement is for lthreshold")
     circle2=PhotoImage(file="accept1.png")
     circle2btn=Button(window2,image = circle2,border =0,bg="white")
     circle2btn.image = circle2
     circle2btn.place(relx=0.4, rely=0.5, relwidth=0.30, relheight=0.12)
     count1()
     today1 = datetime.now()
     d2 = today1.strftime("%d/%m/%Y %H:%M:%S")
     row list = ['Accepted',d2]
     writer = csv.writer(file)
rentdatetime = datetime.now()
     writer.writerow(row list)
     window2.update()
     window2.after(2000,delete img2())
Else:
Accepted
accepted im age is shown as per the validation. Call count1()
function (refer below im age) to count the rejected im ages and
store the result with current date and time in csv file.
 def count1():
      global buttonclick1
      global l1
      buttonclick1 += 1
      l1.configure(text= " 0" + str(buttonclick1))
```

- A gain, the validation tag will only remain in the window up to required time and the window refreshes. So, line 801-804 does that.
- The test im age is autom atically deleted after every first im age, and the line 828-831.
- We have set the live camera and pic resolution to 320x240
- \bullet Open C V live camera is opened using the same syntax and stored in the file using the imwrite inbuilt function from Open C V .
- 8. TOOLS WINDOW.
 - Setting window, labelling, photoim age and function creation goes as above code.

R O S A - I V 1.2

Author's Name: IMPANAS

Pyttsx3 is a text-to-speech conversion library, it works offline and is compatible with both Python 2 and Python 3

- Steps to install pyttsx3 are as follows:
- pip in stall pytts x 3
- Along with pyttsx3,install libespeak as
- sudo apt-get in stall libespeak

Mainly, import pytts x 3 is defined, the code for application of voice is given below:

```
def too():
    engine=pyttsx3.init()
    engine.say("Welcome to rosaa-i")
    engine.runAndWait()
too()
```

A function is defined, where pyttsx3.init() will get a reference to a pyttsx3.engine.say is where a text message is written to speak. Here a text is written as "Welcome to rosa-I" is defined where the output is in the form of speech.

Again, here the function which is defined is called.

> In case 1 of Rejected or Accepted the code is as follows:

```
def hello():
    engine=pyttsx3.init()
    engine.say("Rejected")
    engine.runAndWait()

hello()
```

A function called as hello() is defined ,pyttsx3.init() is used to get a reference to a pyttsx3 where the text called as "Rejected" when this code is executed a speech called rejected is heard to you.

In case 2 Accepted the code is as follows:

```
def welcome():
    engine=pyttsx3.init()
    engine.say("Accepted")
    engine.runAndWait()
welcome()
```

Here, a function is define where,pyttsx3.init() is used to get a reference to pyttsx3 where the text called as "Accepted" when this code is executed a speech called accepted is heard to you.

• The audio is even given to teach which is as follows:

```
def teach():
    engine=pyttsx3.init()
    engine.say("teach")
    engine.runAndWait()
teach()
```

Here, a dialog box is displayed where upon clicking on the teach button a voice is given to it simultaneously as a teach button is clicked.

• The audio is given to the open which is as follows:

```
def whenopen():
    engine=pyttsx3.init()
    engine.say("open")
    engine.runAndWait()
whenopen()
```

Here, a dialog box is displayed where upon clicking on the open button a voice is given to it simultaneously as an open button is clicked.

• The audio is given to the help which is as follows:

```
def whenhelp():
    engine=pyttsx3.init()
    engine.say("help")
    engine.runAndWait()
whenhelp()
```

Here, a dialog box is displayed where upon clicking on the help button a voice is given to it simultaneously as an help button is clicked.

• The audio is given to the tools which is as follows:

```
import pyttsx3
engine=pyttsx3.init()|
engine.say("tools")
engine.runAndWait()
```

Here, a dialog box is displayed where upon clicking on the tools button a voice is given to it simultaneously as an tools button is clicked.

• For the selection of folder where it asks the user to choose the folder, an audio is given to it which is as follows:

```
def choosethefolder():
    engine=pyttsx3.init()
    engine.say("choose folder")
    engine.runAndWait()
choosethefolder()
```

• An audio is given to instruct the user to choose a folder.

